

Garage & repairs

Operations / Core workflow guide

Connect vehicles, job cards and parts.

BUILD STATUS

Development preview 0.1.0. These diagrams describe the shipped core records and state actions. They are not interface screenshots. Full UI walkthrough and live Hostinger acceptance are pending.

The record sequence

1

Vehicles

Create this reference data first.

2

Parts

Create this reference data first.

3

Job cards

References: vehicles, parts

Follow the workflow

Create a vehicle and part, start a job to allocate parts, complete it and mark collection.

BEFORE YOU BEGIN

Sign in, select your workspace and open this system. Create referenced records first. Use fictional data for testing and protect any personal or confidential information.

Know your records

Data reference / Inputs and computed values

Vehicles

Field	Input type	How to use it
Name	text	Plain text, up to 200 characters.
Registration	text	Plain text, up to 200 characters.
Owner name	text	Plain text, up to 200 characters.
Owner phone	text	Plain text, up to 200 characters.

Parts

Field	Input type	How to use it
Name	text	Plain text, up to 200 characters.
Sku	text	Plain text, up to 200 characters.
Stock	quantity	Non-negative; at most three decimals. Transaction quantities must exceed zero.
Unit price	money	Non-negative amount; at most two decimal places.

Know your records

Data reference / Continued

Job cards

Field	Input type	How to use it
Vehicle id	ref	Select a workspace record from vehicles.
Part id	ref	Select a workspace record from parts.
Quantity	quantity	Non-negative; at most three decimals. Transaction quantities must exceed zero.
Description	longtext	Plain text, up to 12,000 characters.
Labour	money	Non-negative amount; at most two decimal places.
Total	computed money	Calculated by the server; not a user input.

Every record also has a workspace identifier, state, version and timestamps. Reference selection and server checks prevent a record from linking to another workspace.

Operate with confidence

Actions, permissions and safe recovery

Available state actions

Record	States	Actions
Vehicles	active	Reference data; no state action.
Parts	active	Reference data; no state action.
Job cards	draft > in_progress > completed > collected	start to in progress, complete to completed, collect to collected

Parts and job totals

- The job total uses selected part cost multiplied by quantity, plus labour.
- Starting a job allocates the requested part quantity once and blocks insufficient stock.
- Completing and collecting update job status; they do not initiate payments or integrate vehicle diagnostics.

Roles and subscription access

Owners, managers and staff can create records while the subscription is active. Viewers can read. Approval, verification, publishing, payroll settlement and journal posting require an owner or manager. Entitlements and record quotas are enforced on the server. Expired subscriptions become read only.

Documents and recovery

- Use the record PDF action for a private document. CSV export requires an eligible plan. Attachments accept PDF/JPG/PNG up to 5 MB per file; demos cannot upload.
- A stale version or repeated action is rejected. Refresh, inspect the saved state and retry only when appropriate. Processed records cannot be edited as drafts.
- A PDF is a snapshot of recorded information. Ordinary business records do not receive the CEO signature, stamp or company seal automatically.